SPECT

Programmers Guide ISAv0.2

Version: 0.1

Git tag: v0.2

Tropic Square August 7, 2023





Version history

Version Tag	Date	Author	Description
0.1	7.8.2023	Vit Masek	Initial version

Version: 0.1 CONFIDENTIAL Page: 1
Git commit: 0491268

Contents

1	Glossary	3
2	Register field types	4
3	Introduction	5
4		6 7 7 7 8 8 8 8 9 10
5	5.1 Operand interpretation 5.2 Instruction Format 5.3 Symbols 5.4 R instructions 5.5 I instructions 5.6 M instructions	11 11 11 12 13 14 15
6	6.1 Configuration registers	16 17 20 20 20 20
7	7.1 Tool requirements	21 21 21 22 22

Version: 0.1 Git commit: 0491268

PI	rogrammers Guide ISAv0.2	CONTENTS
8 REFER		22
9 Open	n Issues	23

Version: 0.1 CONFIDENTIAL Page: 3
Git commit: 0491268

1 Glossary

- **CPU** Central Processing Unit
- **ECC** Elliptic Curve Cryptography
- **SPECT** Secure Processor of Elliptic Curves for Tropic

2 Register field types

Meaning of Register field types is following:

- RW Read-Write field
- **RO** Read-only field
- **WO** Write-only field
- RW W1C Read-Write field, Write 1 to clear
- **RW W0C** Read-Write field, Write 0 to clear
- **RW W1S** Read-Write field, Write 1 to set
- **RW W0S** Read-Write field, Write 0 to set
- **RW W1T** Read-Write field, Write 1 to toggle
- **RW W0T** Read-Write field, Write 0 to toggle

3 Introduction

This document provides a programmer's guide for SPECT. SPECT is a domain specific processing unit targeted for calculations of Elliptic Curve Cryptography (ECC). SPECT provides instructions for calculation with 256 bit numbers and modular arithmetics. SPECT is useful to implement operations/algorithms such as:

- ECDSA Elliptic Curve Digital Signature Algorithm
- ECDH Elliptic Curve Diffe-Hellman




Figure 1: SPECT - Block diagram

Version: 0.1 **CONFIDENTIAL** Page: 6 Git commit: 0491268

4 Programmer's model

SPECT programmer's model consists of:

- 32 x 256 bit general purpose registers (**R0 R31**).
- PC Program counter.
- Zero (Z), Carry (C) and Error (E) flag.
- HW RAR (Return Address Register) stack for nested procedure calls.
- 2048 B read-write memory space in address range 0x0000 0x07FC.
- 512 B write-only memory space in address range 0x1000 0x11FC.
- 2048 B read-only memory space in address range 0x3000 0x37FC.
- 144 B read-only memory space in address range 0x4000 0x408C.
- 144 B read-only memory space in address range 0x4000 0x408C.
- 50 B write-only memory space in address range 0x5000 0x504C.

Note

SPECTs address space is 32 bit word organized. Load and store instructions works with 256 bit values and it always uses 8 consecutive words in the memory. E.g. 0x0020 - 0x003C.




Figure 2: SPECT - Programmers model

Version: 0.1 **CONFIDENTIAL** Page: 7 Git commit: 0491268

4.1 Subroutine calls

SPECT contains HW **RAR** stack, and it pushes return address from subroutine to RAR stack each time when it executes CALL instruction. When SPECT executes RET instruction, it pops value from RAR stack and updates **PC**. HW **RAR** stack supports up to 5 nested subroutine calls.

Note

Behavior of SPECT when number of nested subroutine calls is exceeded is undefined.

4.2 Using private keys

Private keys are typically sensitive information in cryptographic systems. Therefore, it is good to minimize the time for which they are present in such system. When SPECT Program needs to use private key which is stored elsewhere in the system, it executes GPK instruction which reads 256 bit private key from outside of SPECT. GPK instruction supports key identification in case of multiple private keys are available in the system.

4.3 Using random numbers

Proper random numbers with uniform distribution are critical for cryptographic calculations. Such random numbers can be typically generated by TRNG (True Random Number Generator). When SPECT Program needs a random number, it executes GRV instruction which obtains random number from outside of SPECT.

4.4 Modular arithmetics

SPECT provides instructions for finite field arithmetic such as addition, subtraction and multiplication with 256 bit operands stored in general purpose registers. SPECT supports fast multiplication in Ed25519 and P-256 curves finite fields via dedicated instructions – MUL25519 and MUL256. Modular arithmetics with generic modulus specified by value in **R31** is supported by instructions ADDP, SUBP, MULP. SPECT also supports modular reduction of 512 bit number with REDP instruction.

When programming with modular instructions, one needs to be careful about input operands of such instructions. Following conditions must be met:

- op2 < P_{25519} and op3 < P_{25519} for MUL25519 instruction.
- op2 < P_{256} and op3 < P_{256} for MUL256 instruction.
- op2 < R31 and op3 < R31 for ADDP, SUBP instructions.
- R31 != 0 and R31 != 1 for ADDP, SUBP, MULP, REDP instructions.

Version: 0.1 **CONFIDENTIAL**Git commit: 0491268

if these conditions are not met when invoking such modular instruction, result of instruction calculation is undefined (value in op1).

Note

Performance of MULP when **R31** = P_{25519} / P_{256} is lower than performance of MUL25519 / MUL256.

4.5 Hash calculation

SPECT supports SHA512 Hash calculation as specified in FIPS 180-4. SPECT can calculate SHA512 hash from arbitrarily long data stream. When SPECT executes HASH_IT instruction, it resets context in its execution engine to initialization vector as specified in FIPS 180-4. Each execution of HASH instruction processes 1024 bit block, and executes next round of SHA512 calculation.

Note

SPECT does not perform padding of input data as specified in section 5.1 of FIPS 180-4. It is responsibility of SPECT program or external system to perform such padding.

4.6 Handling secret results

Cryptographic calculations frequently result in a shared secret (e.g. in case of ECDH calculation), which shall only be visible to certain other objects in the system, but it shall not be globally accessible on system level memory bus. When SPECT program finishes its execution, it stores these results into **SRR** register. After the program execution has finished, external blocks within a system can read this secret result from the SPECT via dedicated handshake.

4.7 Scalar blinding

SPECT supports scalar blinding by a random number as side-channel counter-measure by SCB instruction. It blinds the scalar sc using group scalar randomization method as defined in [1] with 256 bit random number. The random number rng shall be obtained in advance by GRV instruction as described above. The group order q shall be present in **R31**.

SCB performs this exact function:

$$Blind(sc,rng,q) = q \times (rng|(2^{255}+2^{223})) + sc$$

4.8 SPECT invocation

SPECT is invoked by external system which has access to its memory space via memory bus as shown in following figure:

Version: 0.1 **CONFIDENTIAL** Page: 9

Git commit: 0491268




Figure 3: SPECT - Invocation

Note

Address of first Program instruction executed by SPECT after **COMMAND[START]** = 1 is written, is fixed and defined by a system which integrates SPECT.

4.9 Invalid instructions

When SPECT attempts to execute invalid instruction, it aborts program execution and sets **STATUS[ERR]** = 1.

Note

Invalid instruction means invalid opcode or not matching parity bit in the instruction code. Unless a fault, usual cause of this is e.g. missing RET instruction in subroutine or END instruction at the end of program.

Version: 0.1 **CONFIDENTIAL** Page: 10

Git commit: 0491268

4.10 Soft Reset

SPECT can be reset by extenal system by writing **COMMAND[RST]** = 1. When SPECT is reset, it aborts program execution and resets its internal state.

4.11 Interrupts

SPECT program execution can't be interrupted by an external event (other than Soft reset). SPECT itself can generate following interrupts for external system:

- Program Done Enabled when INT_ENA[INT_DONE_EN] = 1. Generated when SPECT program executes END instruction, or it detects error.
- Program Error interrupt Enabled when INT_ENA[INT_DONE_EN] = 1. Generated when SPECT attempts to execute invalid instruction.

5 Instruction set

SPECT provides 4 types of instructions:

- R Register
- I Immediate
- M Memory
- **J** Jump

5.1 Operand interpretation

All operands are considered as 256 bits unsigneds. Arithmetic instructions working only with 32 bit operands ignores the 224 MSBs of input and clears them in the result. Logic instructions working only with 32 bit operands also ignores the 224 MSBs of input, but passes the 224 MSBs of op2 to the result.

5.2 Instruction Format

31	30 29	28 25	24 22	21 17	16 15 12	11 07	06 00
р	type	opcode	func	op1	op2	op3	R
р	type	opcode	func	op1	op2	lmn	nediate I
р	type	opcode	func	op1		Addr	M
							<u> </u>
р	type	opcode	func			NewPC	J

5.3 Symbols

Following symbols are used in description of instructions:

- || Bitwise concatenation
- $P_{25519} = 2^{255} 19$
- $P_{256} = 2^{256} 2^{224} + 2^{192} + 2^{96} 1$
- F Flags set by the instruction
- #C Number of cycles the instruction takes to execute

Version: 0.1 Git commit: 0491268

5

SPECT Programmers Guide ISAv0.2

5.4 R instructions

Mnemonic	Name	Semantics	F	#C			
32 bit arithmetic instructions							
ADD op1,op2,op3	32 bit adition	op1 = op2 + op3	Z	11			
SUB op1,op2,op3	32 bit subtraction	op1 = op2 - op3	Z	11			
CMP op2,op3	32 bit comparison	op2 - op3	Z	9			
32 bit logic instructions							
AND op1,op2,op3	32 bit bitwise AND	op1 = op2 & op3	Z	11			
OR op1,op2,op3	32 bit bitwise OR	op1 = op2 op3	Z	11			
XOR op1,op2,op3	32 bit bitwise Exclusive OR	op1 = op2 ^ op3	Z	11			
NOT op1,op2	32 bit bitwise NOT	op1 = ~op2	Z	10			
Shift Instructions							
LSL op1,op2	Logic shift left	op1 = op2[254:0] 0	С	10			
LSR op1,op2	Logic shift right	op1 = 0 op2[255:1]	С	10			
ROL op1,op2	Rotating shift left	op1 = op2[254:0] op2[255]	С	10			
ROR op1,op2	Rotating shift right	op1 = op2[0] op2[255:1]	С	10			
ROL8 op1,op2	Rotating byte shift left	op1 = op2[247:0] op2[255:248]		10			
ROR8 op1,op2	Rotating byte shift right	op1 = op2[7:0] op2[255:8]		10			
SWE op1,op2	Swap endianity	op1[255:248] = op2[7:0]		10			
		op1[247:240] = op2[15:8]					
		op1[7:0] = op2[255:248]					
Modular arithmetic instructions							
MUL25519 op1,op2,op3	Multiplication in $GF(P_{25519})$	op1 = (op2 * op3) % P_{25519}		91			
MUL256 op1,op2,op3	Multiplication in $GF(P_{256})$	op1 = (op2 * op3) % P_{256}		139			
ADDP op1,op2,op3	Generic Modular Addition	op1 = (op2 + op3) % R31		16			
SUBP op1,op2,op3	Generic Modular Subtraction	op1 = (op2 - op3) % R31		16			

ر ت	
INSTF	
NCTI	
S NO	
Ĕ	

Mnemonic	Name	Semantics F	#C
MULP op1,op2,op3	Generic Modular Multiplication	op1 = (op2 * op3) % R31	597
REDP op1,op2,op3	Generic Modular Reduction	op1 = (op2 op3) % R31	528
Other Instructions			
MOV op1,op2	Move register	op1 = op2	7
CSWAP op1,op2	Conditional swap	if C == 1 then:	11
		op1 = op2	
		op2 = op1	
HASH op1,op2	Hash	tmp = <i>SHA512</i> (op2+3 op2+2 op2+1 op2)	347
		op1 = tmp[255:0]	
		op1+1 = tmp[511:256]	
GRV op1	Get Random Value	op1 = Random number	-
SCB op1,op2,op3	Blind scalar	B = <i>Blind</i> (op2, op3, R31)	88
		op1 = B[255:0]	
		op1+1 = B[511:256]	

5.5 I instructions

Mnemonic	Name	Semantics	F	#C				
32 bit arithmetic instructions								
ADDI op1,op2,lmmediate	32 bit addition	op1 = op2 + Immediate	Z	11				
SUBI op1,op2,Immediate	32 bit subtraction	op1 = op2 - Immediate	Z	11				
CMPI op2,Immediate	32 bit comparison	op2 - Immediate	Z	9				
12 bit logic instructions								
ANDI op1,op2,lmmediate	12 bit bitwise logic AND	op1 = op2 & Immediate	Z	11				
ORI op1,op2,Immediate	12 bit bitwise logic OR	op1 = op2 Immediate	Z	11				
XORI op1,op2,Immediate	12 bit bitwise exclusive OR	op1 = op2 ^ Immediate	Z	11				

SPECT
Programmers Guide ISAv0.2

Mnemonic	Name	Semantics	F	#C
Other Instructions				
CMPA op2,Immediate	comparison	<pre>if op2 == Immediate then: Z = 1</pre>	Z	9
		else: Z = 0		
MOVI op1,Immediate	Move immediate	op1[11:0] = Immediate, op1[255:12] = 0		6
HASH_IT	Hash init	Reset hash calculation.		9
GPK op1, Immediate	Get Private Key	op1 = Private key, Key index = immediate		_

Due to not enought space in the 32 bit instruction format, the immediate operand is just 12 bit. Because of that, the logic instructions works only with the 12 LSBs of op2. E.g. 0xFF12 & 0xF0F = 0xFF02.

5.6 M instructions

Mnemonic	Name	Semantics	F	#C
LD op1,Addr	Load	op1[31:0] = Mem[Addr]		21
		op1[63:32] = Mem[Addr+0x4]		
		•••		
		op1[255:224] = Mem[Addr+0x1C]		
ST op2,Addr	Store	Mem[Addr] = op1[31:0]		12
		Mem[Addr+0x4] = op1[63:32] =		
		Mem[Addr+0x1C] = op1[255:224]		

5.7 J instructions

Mnemonic	Name	Semantics	F	#C
CALL NewPC	Subroutine call	push(RAR, PC+0x4), PC = NewPC		5
RET	Return from subroutine	PC = pop(RAR)		5
BRZ NewPC	Branch on Zero	if Z == 1 then:		5
		PC = NewPC		
BRNZ NewPC	Branch on not Zero	if Z == 0 then:		5
		PC = NewPC		
BRC NewPC	Branch on Carry	<i>if</i> C == 1 <i>then:</i>		5
		PC = NewPC		
BRNC NewPC	Branch on not Carry	<i>if</i> C == 0 <i>then:</i>		5
		PC = NewPC		
JMP NewPC	Unconditional jump	PC = NewPC		5



SPECT
Programmers Guide ISAv0.2

6 SPECT Memory Map

Base Address: 0x0000 0000 End Address: 0x0000 9FFF

Memory region	Address offset range	Size	
Data RAM IN	0x0000 0000	2 KB	
Data KAWI IIV	0x0000 07FF		
Data RAM OUT	0x0000 1000	512 bytes	
Data RAIVI OOT	0x0000 11FF	312 bytes	
Configuration registers	0x0000 2000	1.C by toc	
Configuration registers	0x0000 200F	16 bytes	
Constants DOM	0x0000 3000	2 1/D	
Constants ROM	0x0000 37FF	2 KB	
External Manager (In	0x0000 4000	C4 by toc	
External Memory In	0x0000 403F	64 bytes	
Fytornal Momory Out	0x0000 5000	00 by too	
External Memory Out	0x0000 504F	80 bytes	
Instruction Mamon	0x0000 8000	0 1/D	
Instruction Memory	0x0000 9FFF	8 KB	

6.1 Configuration registers

Base Address: 0x0000 2000 **End Address:** 0x0000 200F

Address Offset	Register Name	Reset Value
0x0	BLOCK_ID	0x000-0030
0x4	COMMAND	0x00000000
0x8	STATUS	0x0000001
0xc	INT_ENA	0x00000000

6

SPECT
Programmers Guide ISAv0.2

Register name:		BLOCK_ID			
Address:		0x2000			
Field Type		Reset	Bits	Description	
		value			
ID_CODE	RO	0x30	15:0	Identification code	
REV_CODE	RO	-	19:16	Revision code	

Register name:		COMMAND			
Address:		0x2004			
Field Type		Reset	Bits	Description	
		value			
START	WO	0x0	0:0	Starts SPECT FW operation	
	W1S;				
SOFT_RESET	WO	0x0	1:1	Stops FW execution and resets SPECT	

Register name:		STATUS			
Address:		0x2008			
Field	Type	Reset value	Bits	Description	
IDLE	RO	0x1	0:0	SPECT is in IDLE mode	
DONE	RW W1C	0x0	1:1	Active when SPECT successfully completes the calculation	
ERR	RW W1C	0x0	2:2	Active when SPECT ends the calculation with error	

Register name:	INT_ENA

Page: 19

SPECT
Programmers Guide ISAv0.2

Address:		0x200c			
Field	Type	Reset value	Bits	Description	
INT_DONE_EN	RW	0x0	0:0	Enables DONE interrupt	
INT_ERR_EN	RW	0x0	1:1	Enables ERROR interrupt	

6.2 Data RAM IN

Data RAM IN is a memory where external system stores parameters for SPECT Program before it starts its execution. SPECT Program sees it as read-write memory.

6.3 Data RAM OUT

Data RAM OUT is a memory where SPECT Program stores results of its calculation, and external system reads such results after SPECT Program execution ends. SPECT Program sees it as write-only memory.

6.4 Instruction Memory

Instruction memory contains the Program executed by SPECT. Based on SPECT manufacturing configuration, this memory might be readable/writable by external system (Instruction Memory is RAM), or not accessible by external system at all (Instruction Memory is ROM with fixed program). SPECT Program do not have access to this memory with LD and ST instructions.

6.5 Constant ROM

Constant ROM contains a ROM image with important cryptographic constants used by SPECT Program during program execution. SPECT program sees it as read-only memory. **Open Issue 1: Place SPECT Constant ROM content!**

Version: 0.1 Git commit: 0491268

7 SW toolchain

SPECT contains SW toolchain intended for SW development and debugging. SPECT has following applications available:

- spect_compiler A compiler/assembler which creates .hex file from .s assembly file.
- spect_iss Instruction level simulator with simple command line debugger. It can simulate .s file as well as .hex file.

Options for each of the applications are described when using - -help command line option. Options available inside interactive shell of **spect_iss** are available with - -help command line oprion or **help** command.

SPECT assembler has support for following assembly language features:

- Function labels
- Constant definitions
- Include other assembly file

7.1 Tool requirements

SPECT SW toolchain requires following tools:

CMAKE 3.18.2 or higher

Open Issue 2: What else?

7.2 Function labels

SPECT compiler allows definition of function labels, and passing them as NewPc of J instructions, e.g like so:

```
_start:
CALL my_func
END

my_func:
ADD r0, r1, r2
RET
```

Version: 0.1 Git commit: 0491268

7.3 Constant definitions

SPECT compiler allows definition of constants, and passing them as Addr of M instructions or Immediate operand of I type instructions like so:

```
threshold .eq 0x12
_start:
ADDI r0, r0, threshold
```

```
p25519_addr .eq 0x3020
_start:
LD r31, p25519_addr
```

Note

Currently, SPECT compiler does not support expression parsing, it only supports simple decimal, hexadecimal or binary value when defining constants.

7.4 Include other assembly file

Multiple .s assembly files can be connected together in SPECT source code via "include" directive, e.g. like so:

```
_start:
NOP
.include <other_s_file>
END
```

8 REFERENCES

References

[1] Danger, Jean-Luc et al. "A synthesis of side-channel attacks on elliptic curve cryptography in smart-cards." Journal of Cryptographic Engineering 3 (2013): 241 - 265.

9 Open Issues

Document contains following open issues:

Open Issue 1: Place SPECT Constant ROM content!

Open Issue 2: What else?